

Release Note

Community Connect 4[®]

Driver Update 098



Important For more information on CC4DRV098 please refer to Driver Update 98 for Community Connect 4 networks (DWN4834266) on the RM Support Web site.

For the latest information on all CC4 Update Tasks, refer to the Community Connect[®] 4 Software Updates – Overview Guide (TEC1255704) on the RM Support Web site.

CC4DRV098 is intended for use on Community Connect 4 (CC4) networks **only**.

Introduction

This Release Note includes:

- An overview of CC4 Driver Update CC4DRV098.
- Instructions on how to install this Driver Update on your Community Connect 4 network. This Release Note assumes you have successfully downloaded the Driver Update file from the Knowledge Library article DWN4834266.
- Reference tables listing the CC4 hardware drivers showing those added or updated by CC4DRV098.

Contents checklist

The Driver Update includes:

- This Release Note
- RM CC4DRV098

Overview

CC4DRV098 updates the RM build area on the Community Connect 4 server to allow Windows 10 64-bit rebuilds of the following hardware:

- Toshiba Satellite Pro NB10t-A-11G

Installing CC4DRV098

Follow the instructions below to install this Driver Update on the Forest Root domain controller server:

► **To install CC4DRV098**

1. Download CC4DRV098.exe as described in DWN4834266.
2. Ensure that you are logged on to the Forest Root domain controller server as a Windows administrator user (not as an RM system administrator).
3. Copy the Driver Update to a temporary location (e.g. D:\temp).
4. Run the Driver Update by double-clicking the disk icon for the self-extracting executable file (CC4DRV098.exe) and click Install. The Driver Update will extract files and run the RM Installation Assistant to begin the installation. When prompted, click Continue. The installation will proceed automatically.
5. When prompted that the RM Installation Assistant has finished, click Finish.

Adding Build Critical Drivers to your Build Disks

Some build critical drivers will need to be added to your build disks before you regenerate the Build Disk for the supported hardware. Please note that each build critical driver should only be added to build disks based on the corresponding Windows Preinstall Environment (WinPE) version. The WinPE version of a build disk can be checked by viewing the build disk's name from within the RM Management Console. When creating a build disk the WinPE version can be specified by selecting the appropriate base build disk. The following drivers should be added to the build disks that have corresponding WinPE versions to allow the supported hardware to be built:

Driver Description	Driver Version	Driver Manufacturer	WinPE Version Supported
Toshiba Satellite Pro NB10t-A-11G WinPE 10 LAN Driver	8.20.815.2013	Realtek	Windows PE 10

Troubleshooting

If you experience any problems related to the hardware drivers installed in this update, before contacting RM Support, **first** check the tables in *CC4DRV098 Driver Revisions* section below to verify that the correct versions are present on your network.

Newer revisions of drivers may get installed by default as they may match in other hardware updates. In this event, the drivers below can be manually selected when rebuilding the computer. The drivers added as part of this update have the RM System model number as part of the driver description.

CC4DRV098 Driver Revisions

The driver revisions that have been added or updated as part of CC4DRV098 are shown in **bold** in the following tables.

RM System	Device	Driver Manufacturer	Driver Version	Operating System
Toshiba Satellite Pro NB10t-A-11G	LAN	Realtek	8.20.815.2013	Win 10 64-bit
Toshiba Satellite Pro NB10t-A-11G	Card Reader	Alcor Micro, Corp	1.0.38.135	Win 10 64-bit
Toshiba Satellite Pro NB10t-A-11G	Trusted Execution Engine Interface	Intel	1.1.0.1064	Win 10 64-bit
Toshiba Satellite Pro NB10t-A-11G	Audio	Realtek	6.0.1.7058	Win 10 64-bit
Toshiba Satellite Pro NB10t-A-11G	Chipset Utility	Intel	9.4.4.1005	Win 10 64-bit
Toshiba Satellite Pro NB10t-A-11G	System Driver	Toshiba	1.00.0033.0	Win 10 64-bit
Toshiba Satellite Pro NB10t-A-11G	Patch files	Toshiba	1.0	Win 10 64-bit
Toshiba Satellite Pro NB10t-A-11G	Graphics Post Install	Toshiba	1.0	Win 10 64-bit

*Please see below for further details on device manager versions of the drivers.

Device	Version	Operating System
Intel(R) Pentium(R) processor N- and J-series / Intel(R) Celeron(R) processor N- and J-series SoC Transaction Router - 0F00	9.4.4.1005	Win 10 64-bit
Intel(R) Pentium(R) processor N- and J-series / Intel(R) Celeron(R) processor N- and J-series PCI Express - Root Port 2 - 0F4A	9.4.4.1005	Win 10 64-bit
Intel(R) Pentium(R) processor N- and J-series / Intel(R) Celeron(R) processor N- and J-series PCI Express - Root Port 3 - 0F4C	9.4.4.1005	Win 10 64-bit
Intel(R) Pentium(R) processor N- and J-series / Intel(R) Celeron(R) processor N- and J-series PCI Express - Root Port 1 - 0F48	9.4.4.1005	Win 10 64-bit
IWD Bus Enumerator	4.5.61.0	Win 10 64-bit